



ETM[®] System

Knowledge Base Article #ETM686, Rev C

Upgrading to v9.0.0 Build 22 from v7.1.1 Build 41 or Later of the ETM[®] System on Windows

Synopsis

This article explains how to upgrade to v9.0.0 Build 22 from v7.1.1 Build 41 or later of the ETM[®] System on Windows. If you are upgrading from an earlier version, contact SecureLogix Technical Support before beginning the upgrade.

IMPORTANT NOTES

- The ETM System supports only 64-bit operating systems; 32-bit systems are no longer supported.
- Ensure that you are running a supported version of Oracle before you continue. Oracle 12c R2, 18c, and 19c (Enterprise or Standard) are supported.
- Upgrade the Management Server/Report Server systems first and then ETM Client systems afterwards.
- You cannot upgrade a UTA Appliance from a previous version to v9.0.0, due to the operating system upgrade. You must uninstall the previous version and then install the v9.0.0 UTA Appliance. Note that the 7.x UTA Appliance connects to and interoperates with the 9.0.0 Management Server.
- **<INSTALL_DIR>** is used in these instructions to refer to the directory where the ETM System software is installed. **IMPORTANT:** In this release, the default path has been changed to **C:\apps\SecureLogix\ETM..** Ensure that you change the path on the installer screen to point to your current installation directory when performing the upgrade.

Steps

1. **Connect to the database via the Database Maintenance Tool.** Verify that no errors exist before beginning the upgrade. If errors are present, contact SecureLogix Technical Support before you continue. See the *ETM[®] System Administration and Maintenance Guide* for instructions for using the Database Maintenance Tool, if necessary.
2. **Shut down any running ETM System applications.**
 - Close all ETM Client applications.
 - Shut down all ETM Management Server and Report Server instances, using the Windows Services Control Panel.
 - If multiple ETM Management Server or Report Server instances are running on the machine, deregister all application instances with the Service Control Manager using the **AppManager.exe** utility as follows:
 - a. Open a command prompt window and change to the ETM Server installation directory.



- b. Obtain a list of the registered application instances by typing the following at the prompt:

```
AppManager /list /type:both
```

- c. For each instance ID in the list, type the following command at the prompt:

```
AppManager /remove /type:both /ID:<instance_id>
```

3. **Install the ETM System v9.0.0 software as Administrator.** Run the installer (**setup.exe**) from the software installation media and follow the onscreen prompts. **IMPORTANT:** Ensure that you change the installation path on the installer to point to the directory where the ETM Software is currently installed.

The installer automatically removes the previous version and backs up certain files that may have been user-modified.

- **IMPORTANT** Be sure to upgrade all remote ETM System Clients before trying to use them to connect to the upgraded ETM Server.
- When the ETM Management Server is uninstalled, the following files are automatically backed up from the <INSTALL_DIR> to the <INSTALL_DIR>\Backup\MS_<DATE_TIME> directory:
 - **delivery.properties**
 - **ETMManagementService.cfg**
 - **npconfig.properties**
 - **smdr.properties**
 - **twms.properties**
 - **\ps\software_repository\package**—Entire directory, which contains the appliance software packages. The files also remain in the original directory.
 - **\ps\software_repository\smdr**—Entire directory, which contains the SMDR parse files. If a file with a default name has been user-modified, it must be restored to the ETM Server <INSTALL_DIR>\ps\software_repository\smdr\ directory after upgrade. User-defined files with custom names are not deleted nor overwritten during upgrade and therefore do not need to be restored.
 - **\ps\software_repository\ini**—Entire directory, which contains the Dialing Plans. Upon upgrade, the Dialing Plans installed on the Appliances are not deleted, but user-modifications to the Dialing Plans need to be copied to new Dialing Plan file in the <INSTALL_DIR>\ps\software_repository\ini\ directory on the ETM Server and then reinstalled on the Spans.
- When the ETM Report Server is uninstalled, the following files are automatically backed up to the <INSTALL_DIR>\Backup\RS_<DATE_TIME> directory:
 - **ETMReportService.cfg**
 - **twms.properties**

Refer to the *ETM[®] System Installation Guide* for detailed software installation instructions, if necessary. PDFs of all of the ETM System user guides are located on the ETM software



installation media in the top-level **Documentation** folder.

4. **Restore custom configuration files.**

- Use a tool such as **CompareIt** to identify customization in the backed-up **.properties**, **.cfg**, and **.ini** files listed in step 2. Copy those changes into the newly installed files so that any updates in the files are retained. Do not copy over the new files, because they may contain new settings for this release.
- **SMDR parse file**—Copy the custom SMDR parse file(s) to the `<INSTALL_DIR>\ps\software_repository\smdr` folder (*not necessary if the files had custom names, since they were not overwritten nor deleted*).

5. **Copy the database driver and required jar files to required locations.** Copy the database driver that corresponds to the version of Oracle you are running from the Oracle installation to each of the following ETM System installation directories. Also copy the **oraclepki.jar**, **osdt_cert.jar**, and **osdt_core.jar** files to these directories on systems using Oracle 12.2.

- The ETM Server.
- Any remote Report Server.
- Any remote ETM Database Maintenance Tool.

Remote ETM System Consoles do not require the driver file.

6. **Connect to the database.**

IMPORTANT If you are applying this update to a system that requires the new TNS Names connection string format, continue with “Updating the Database to Allow Use of a TNS Names Connection String” on page 5 before continuing. If the system can use the “quick connect” string for the upgrade, those steps are not needed, and you can continue with the steps below.

- a. Start the **ETM Database Maintenance Tool** and connect to the Database.
- b. You are prompted to upgrade the database. Click **Yes**. (If any errors occur while upgrading the database, note the error and call Technical Support at the number at the bottom of this article.)
- c. Right-click the data instance the ETM Server uses and click **Set as Default**. (Not necessary if you returned the backed up **twms.properties** file to the `<INSTALL_DIR>`, since that information is already included in the file.)

7. **Recreate multiple Management Server and Report Server instances, if these are used.** If multiple instances of the Management Server and Report Server are in use, use the **AppManager** utility to recreate the instances removed in Step 1. Refer to “Creating Multiple Application Instances” in the *ETM[®] System Technical Reference* for detailed instructions.

- If multiple instances were in use before the upgrade, the instance-specific **twms.properties** files were not changed nor deleted and therefore should require no modification. Recall that the values in the global **twms.properties** file are used unless explicitly overridden by a value in the instance-specific file; therefore, any new fields in the global file are implemented in the instances. If a specific instance needs a different value, specify that value in the instance-specific file. If all instances need a different value, you can change it once in the global file and it will apply to all



instances.

8. **Start the ETM System applications and verify operation.** Perform the following for each set of Server instances:
 - a. Start the ETM Server and Report Server. Check for errors in the **error** and **server-fatal.log** files. The **server-fatal.log** is stored in the root of the **<INSTALL_DIR>** and is only present if the ETM Server terminates unexpectedly. The error logs are stored in the **<INSTALL_DIR>\ps\errors** directory.
 - b. If no errors appear, start the ETM System Console, log in to the Server, and then open the Performance Manager.
 - c. Verify that all Cards have reconnected and no errors are present. If errors are present, contact SecureLogix Technical Support for assistance before continuing.
9. **Uninstall any existing UTA Appliances of a previous version and then install and configure the v9.0.0 UTA Appliances.** Note that the v7.1.x UTA Appliances will connect to the v9.0.0 Management Server, giving you time to complete the upgrade without taking all of them out of service at once. After you install the 9.0 UTA Appliance, you can import the configuration from the 7.1.x Appliance. Optionally, you can choose to continue using the existing 7.1.x UTA Appliances if you do not want to install the 9.0.0 version. However, DO NOT attempt to push the 9.0 Appliance package to UTA Appliances of a previous version. If you erroneously attempt to push the 9.0 package to a 7.1.x UTA Appliance, it will fail to process the package and continue running its current software version.
10. **Upgrade the Card software (Not on UTA).** After the Cards connect to the Server, install the included 7.1.90 packages on all SIP, TDM, and dedicated CRC* Appliances (if they are not already running that version) using the software installation mechanism in the GUI. See the *ETM[®] System Administration and Maintenance Guide* for instructions for installing Card software. You can view the progress of the upgrade in the **Status Tool** and **Diagnostic Log**.

IMPORTANT: Do not attempt to upgrade the Card software on an existing UTA Appliance of a previous version to the 9.0 package. You must first completely uninstall the previous 7.1.x UTA Appliance and then install the 9.0.0 UTA Appliance if you want to upgrade to the v9.0 UTA Appliance. You can, however, upgrade the software on deployed 7.1.x UTA Appliances to the 7.1.90 package, if they are not already running that version.

**Does not apply to the EOL 1060.*

IMPORTANT:

- It is imperative that you do not reboot or power cycle the Card while the software is being downloaded until the upgrade and software installation is complete. The Card automatically reboots when the upgrade is complete. If you believe the Card has become unresponsive, be certain that 15 minutes have elapsed since you began and call SecureLogix Technical Support. Do not manually power cycle or reboot the Card.
- **IMPORTANT Information about upgrading UTA and the inline SIP application:**
 - **For graduated SIP software upgrades, Call Recording functionality requires components to be upgraded in a specific order**— If you want to upgrade one SIP Appliance proxy component first and let it run for an extended amount of time before



upgrading the other proxy component, then the Signaling Proxy should be upgraded first to ensure media continues to be anchored. This is not an issue if both components are upgraded in a timely manner.

- **When installing software on an inline SIP or UTA Appliance**, additional steps are required compared to other appliance models. You first push the software package to the Call Processor at the Card level, which then makes it available on the signaling and media proxy nodes. You must then activate the new software on each of the proxy nodes.

For instructions, see the *ETM[®] System Administration and Maintenance Guide*.

11. **Update the CCMI file.** Download the new CCMI file from the SecureLogix website, place it into the ETM Directory, and import the new CCMI file: https://support.securelogix.com/ccmi_login.htm
12. **Remove backup files.** When the upgrade is complete and the ETM System is verified to be operating correctly, both manually and automatically created backup directories can be deleted to free the hard drive space they use.

Updating the Database to Allow Use of a TNS Names Connection String

These steps are needed when upgrading to 9.0.0b22 on a system that already requires the new connection string format, and also when immediately going to the new connection string format (such as when migrating to a new database that only allows the new format). If you are applying this update to a system where you can use the “quick connect” string to install and configure the Database, or upgrading a system that does not use the TNS Names format, these steps are not required.

To update the Database to use the TNS Names format connection string

1. Perform Steps 1-5 above.
2. Connect to the Database Instance in SQL Plus, and issue the `describe parent_db;` command. Output similar to the following appears:

```
SQL> describe parent_db;
```

Name	Null?	Type
PARENT_ID	NOT NULL	VARCHAR2(1024)
IP_ADDR	NOT NULL	VARCHAR2(255)
PORT	NOT NULL	NUMBER
INSTANCE_NAME	NOT NULL	VARCHAR2(255)
SCHEMA_NAME	NOT NULL	VARCHAR2(255)

```
SQL>
```

3. Issue these commands:

```
SQL> ALTER TABLE PARENT_DB ADD ( custom_connection_string VARCHAR(255) NULL );
```



Table altered.

```
SQL> ALTER TABLE PARENT_DB ADD ( use_custom_connection_string CHAR(1) DEFAULT '0' NOT NULL );
```

Table altered.

4. Issue the `describe parent_db;` command again. The new format below is displayed:

```
SQL> describe parent_db;
```

Name	Null?	Type
PARENT_ID	NOT NULL	VARCHAR2 (1024)
IP_ADDR	NOT NULL	VARCHAR2 (255)
PORT	NOT NULL	NUMBER
INSTANCE_NAME	NOT NULL	VARCHAR2 (255)
SCHEMA_NAME	NOT NULL	VARCHAR2 (255)
CUSTOM_CONNECTION_STRING		VARCHAR2 (255)
USE_CUSTOM_CONNECTION_STRING	NOT NULL	CHAR (1)

```
SQL>
```

5. Connect to the Database Instance in the Database Maintenance Tool using the new connection string. It will ask if you want to change the format of the connection string from the old format to the new format. Click **Yes**. It will then say the database is out of date and needs to be updated Click **Yes**. After the validation completes, the Database is updated and ready for use. (If any errors occur while upgrading the database, note the error and call Technical Support at the number at the bottom of this article.)
6. Right-click the data instance the ETM Server uses and click **Set as Default**. (Not necessary if you returned the backed up **twms.properties** file to the **<INSTALL_DIR>**, since that information is already included in the file.)
7. Continue with Step 7 above.

Current Software Versions:

- ETM Client and Server applications—9.0.0 Build 22
- Appliance packages:
 - UTA—9.0-12
 - All other Appliance types*—7.1.90

*Does not apply to the EOL 1060.

Note: For SIP Proxy installations, refer to [APP258 - SIP Proxy Appliance Build 7.1.91 Release Notes](#) for information about a special case regarding the way TCP response messages are handled by some SBCs running older versions of their software.



Last Update: 4/6/2022



SecureLogix Corporation

13750 San Pedro, Suite 820 • San Antonio, Texas 78232 • (210) 402-9669 • www.securelogix.com

Support (877) SLC-4HELP • EMAIL support@securelogix.com • <https://support.securelogix.com>

ETM, We See Your Voice, SecureLogix, SecureLogix Corporation, and the SecureLogix Emblem are registered trademarks or registered trademarks and registered service marks of SecureLogix Corporation in the U.S.A. and other countries. PolicyGuru is a registered trademark of SecureLogix Corporation in the U.S.A.. All other trademarks mentioned herein are believed to be trademarks of their respective owners.

© Copyright 2020-2022 SecureLogix Corporation. All Rights Reserved. SecureLogix technologies are protected by one or more of the following patents: DE 1,415,459 B1, FR 1,415,459 B1, and GB 1,415,459 B1. U.S. Patents Pending.