



Defining a Custom Allow Regex for Blacklist Allow Rules

Summary

By default, PolicyGuru® SEP Blacklist Allow Rules use the following Regex: **!a^!guaranteed no replacement!**. You can define a custom Regex to use in Blacklist Allow Rules instead of the default. See the instructions below.

More Information

To change the Allow Regex for Blacklist Rules

1. On the **Project Explorer** pane main menu, click the down arrow and click **cep2sep**.
2. Close any open SEP Rules.
3. Click the down arrow next to **Domain Specific Language Definitions** to expand the subtree.
4. Click **SEP Language**. It opens in the **DSL Editor**.
5. Scroll down to the **[then]** entries.
6. Below **[then]Allow the calls=\$sep.doRuleAction("ALLOW", "!a^!guaranteed no replacement!")**, add the following line, substituting your preferred Regex for the example Regex shown in red here:

```
[then]AllowREGEX=$sep.doRuleAction( "ALLOW",  
"!&slclb;^.*&slcrb;!sip:authorized&slcbs;1@securelogix!" );
```

7. On the **DSL Editor** main menu, click **Save**.
8. On the **DSL Editor** main menu, click the **X** to close the editor.
9. To define SEP Blacklist Rules using the Regex you specified, select **AllowREGEX** instead of **Allow the calls** as the **Then** statement.

Note: The new **AllowREGEX** option is not available in any Rules that were open when you added it until you close and reopen the Rule.



SecureLogix Corporation

13750 San Pedro, Suite 820 • San Antonio, Texas 78232
(210) 402-9669 • www.securelogix.com

Support (877) SLC-4HELP • EMAIL support@securelogix.com • support.securelogix.com

ETM, We See Your Voice, SecureLogix, SecureLogix Corporation, and the SecureLogix Emblem are registered trademarks or registered trademarks and registered service marks of SecureLogix Corporation in the U.S.A. and other countries. PolicyGuru is a registered trademark of SecureLogix Corporation in the U.S.A. All other trademarks mentioned herein are believed to be trademarks of their respective owners.

© Copyright 2019 SecureLogix Corporation. All Rights Reserved. This product is protected by one or more of the following patents: US 6,249,575 B1, US 6,320,948 B1, US 6,687,353 B1, US 6,718,024 B1, US 6,760,420 B2, US 6,760,421 B2, US 7,133,511 B2,



US 7,231,027 B2, US 7,440,558 B2, US 8,150,013 B2, CA 2,354,149, DE 1,415,459 B1, FR 1,415,459 B1, and GB 1,415,459 B1. U.S. Patents Pending.